

Release Notes

Studio RM 3.1 (Update 4)



© Copyright 2026 Datamine Software

All Rights Reserved Confidential and Proprietary

Published: 09 March 2026

Legal Disclaimer

The product described in this documentation may be connected to, and/or communicate information and data via, a network interface, which should be connected to a secure network. It is your sole responsibility to ensure a secure connection to the network and to establish and maintain appropriate measures (such as but not limited to the installation of firewalls, application of authentication measures, encryption of data, installation of antivirus programs, etc.) to protect the product, the network, your systems, and the interface against any kind of security breach, unauthorised access, interference, intrusion, leakage, damage, or corruption or theft of data. We are not liable for damages or losses related to any such security breach, unauthorised access, interference, intrusion, leakage, damage, or corruption or theft of data.




Contents

Overview	5
Further Information	5
Studio RM 3.1 (Update 4) Release Notes	6
All Improvements	6
Cut & Fill Consistency	6
Commands & Processes	6
Studio RM 3.1 Release Notes	8
Key Improvements	8
Implicit Modelling Improvements	8
Estimation Improvements	8
Drillhole Importer	8
Dynamic Anisotropy Estimation Support	8
Leapfrog Data Import	9
Digitise Doughnuts!	9
Multiple File Loads	10
Legend Tools Update	11
COMPDH Field Improvements	11
Geosoft® Driver	11
Safer Scripting	12
Ribbon Standardization	12
Early Access Features	13
Other Command & Process Updates	14
All Improvements	16
Commands & Processes	16
Utilities & Supporting Services	20
Defect Fixes	22
Studio RM 3.0.1 Release Notes	26
All Improvements	26



Commands & Processes	26
Automation	26
Defect Fixes	26
Studio RM 3.0 Release Notes	28
New Datamine File Format	28
Plots Overhaul	29
Residual Composites	29
3D Window Improvements	29
Assign Lithology Improvements	30
Filled Wireframe Intersections (Preview)	30
Text Importer	31
Datamine File Tags	31
New Processes & Commands	32
Command & Process Improvements	32
All Improvements	33
Commands & Processes	33
User Experience	36
Automation	37
Utilities & Supporting Services	37
Documentation & eLearning	38
Additional Defect Fixes	39

Overview



Studio RM is the world's leading integrated software package for the natural resource industries. Typical uses are in data capture and analysis, exploration, geology, geochemistry, rock mechanics and orebody modelling. It has been chosen for commodities as diverse as iron ore, gold, nickel, phosphates, diamonds, copper, bauxite, coal, lignite, platinum, petroleum, and industrial minerals.

Studio RM is one of several products in the Studio product family, which includes:



Studio EM for exploration data analysis and modeling.



Studio Geo is for geological and structural modeling.



Studio Mapper for geological face mapping and reporting.



Studio NPVS+ for strategic open pit optimization, design and enhanced scheduling.



Studio OP for open pit design and operational scheduling.



Studio RM for mine geology, reserve modeling and resource estimation.



Studio Survey for open pit and underground mine surveying and reporting.



Studio UG for underground mine design and scheduling.

Further Information

This document includes cumulative releases notes for [[[Undefined variable General.VersionNumber]]]. As such, release notes are listed for all minor updates of the current major version, in reverse chronological order.

Release notes for other versions of Studio RM are available via the Datamine Customer Support website. For more details, see <https://www.dataminesoftware.com/support/>.

For the complete Studio RM documentation, see <https://docs.dataminesoftware.com/StudioRM>.

Studio RM 3.1 (Update 4) Release Notes

This is an interim maintenance release to provide urgent software changes for customers outside of the typical release program cadence. When installing this software, it is recommended that you uninstall any previous copies of Studio RM beforehand.

All Improvements

Cut & Fill Consistency

The key change for this interim update is 'match triangulation', updating DTM generation and reporting functions to ensure that tasks relying on consistent surface generation, don't generate unexpected trivial data fragments in unmined areas due to a mismatch between triangle mapping of shared point locations. This logic works in parallel with existing fragment removal options, which remain available.

Make DTM, both the process and the command, have been updated to allow for the selection of a reference DTM(s) during creation of the new DTM. Cut and Fill has been updated to include the **Match surface triangulations** option for use with existing DTMs selected as part of the Cut and Fill input.

Commands & Processes

- **CORE-10156** You can now specify a reference surface when using the MAKEDTM process.
- **CORE-10109** We have improved the Cut and Fill tool to automatically filter out tiny "noise solids" where surfaces match, giving you cleaner, more meaningful results without sacrificing accuracy in mined areas.
- **CORE-10108** We have added an option in Make DTM to reuse triangulation from a reference surface so overlapping areas with identical XYZ data generate exactly the same triangles for highly consistent volumes. This also appears on the Make DTM screen as "Make diagonals consistent".
- **CORE-10101** The **MAKEDTM** process has a new parameter (@DIAGONAL) to emulate the "Make Diagonals Consistent" switch of the interactive dtm-create screen.

- **CORE-10034** The "Make Diagonals Consistent" DTM feature is now accessible from a script.

Studio RM 3.1 Release Notes

Key Improvements

Implicit Modelling Improvements

- You can now choose to model all, selected and/or visible data in any of the implicit modelling commands (Vein, Contact Surface, Categorical Value and Grade Shells).
- Control the density of output contact surface data using a new Resolution control.
- By default, all implicit modelling commands now default to snap surface data to the drillhole milestone data positions.
- You can now colour Contact Surface symbols, additional points, output surface and output contact points using the colour of the stratigraphy.

Estimation Improvements

- You can now use the **Show Samples** function to view samples contributing to a particular estimated field and estimation reference, using new controls on the **Estimate** ribbon.

This is useful where a parent cell includes multiple domains and you are using zonal control or soft boundaries. Just pick the estimated field and estimation reference number to filter the output of the **Show Samples** command.


Drillhole Importer

Drillhole Importer now recognizes even more field names when automatically mapping to system fields, saving time during the initial phase of importation.

Dynamic Anisotropy Estimation Support

When defining an estimation, you can now choose between Flay lying (horizontal or sub-horizontal) or Inclined (dipping) structural orientation. This introduces the same flexibility already present in the `ANISOANG` process.

Leapfrog Data Import



You can now import Leapfrog mesh (.msh) and Leapfrog Project Model (.lfm) files using a new Data Source Driver. Data is imported as wireframes.

If importing a Leapfrog Project Model file, you can choose to import all associated mesh data or a subset, and can choose the attribute to use to store the original mesh name, making downstream data management much easier.

The new formats are also supported by Studio's drag-and-drop facility, meaning you can drag one or more files into the 3D view and default load settings are used to create the relevant objects in memory and display them.

Digitise Doughnuts!

A new design command (`digitise-doughnut`) lets you create closed string data with internal voids. You select the non-overlapping and fully concentric closed string data and a new closed shape is formed automatically. This is particularly useful where you need to, say, capture the shape of internal void structures in a particular rock zone, or in any situation where an enclosed internal structure needs to be represented.



The new command works really well in relation to polygonal map features and outlines. You can even create multiple layers of structure 'nesting' and input closed strings can be at any orientation, providing the internal structures are fully enclosed without overlaps or crossovers.

You can control how new data is created using a new switch (`doughnut-storage-switch`) to choose between modifying an existing perimeter or generating completely new string data.

Multiple File Loads


You can now import or load multiple files in one operation using new multi-file options. Just pick the files you want to load using a simple browser, and Studio does the rest. You still get to specify load and importation settings, including those specific to a particular driver, but now you can complete the process in a fraction of the time.

To access this function, click **Add to Project** or **External** on the **Data** ribbon and pick your files.

Either import multiple files to the project or load them directly into memory. These files can be of the same type and format or different ones, meaning you can pick a batch of files of various formats (CAD, BMF, DMX and more) and either add them to the project or load and display them after importation and conversion. This makes light work of importing files from other projects and applications.

To use the previous driver selection method, use a menu option to pick a data type or select the new "by driver" option for project import.

Legend Tools Update



3D properties and similar screens now use a clearer and expanded toolset for legend management.

You can still display and edit legends as before, but now there is a dedicated button to create a new legend and (reinstating previous, reportedly popular behaviour) a new button appears to either select the current default legend for the selected column or set the current legend as the default for the current column (with no further prompts or popups).

We've also added the ability to add any colour chip to the unique legend item table in the New Legend Wizard

COMPDH Field Improvements

COMPDH now supports up to 5 ZONE fields to composite within, and five optional fields **DOM1** to **DOM5** can now be specified to record dominant categorical values (by length) within each composited sample. **DOM1** to **DOM5** can be a combination of numeric or up to 32 character alpha fields.

Geosoft® Driver

Geosoft Voxel Models files represent useful geophysical files, also known as *UBC voxel models*. These files contain geophysical inversion data. An import comprises 2 or more files - one file to define the geometry, and 1 or more files containing data values associated with the cells.

To support this new file type a new *Geosoft* option is available on the **Data Import** screen.


Safer Scripting

To maintain the highest level of local data security, we've rigorized our scripting interface in Studio products to provide a way to securely instantiate approved ActiveX objects through automation scripts. This provides a safer and more marshalled automation environment.


In brief, we've introduced a new Studio application method (`CreateObject`) that can be used in place of the deprecated `new ActiveXObject("Prog.ID");` instruction. A call to something like `window.external.System.CreateObject("Prog.ID");` allows approved ActiveX objects to be instantiated to support your scripts. Most importantly, the ones that provide the highest risk are blocked.

The **Datamine Studio Script Updater**, accessible via your **Home** ribbon, can update your scripts either individually or as a batch, automatically making them safer to use.

If you load a script that looks like it could benefit from additional protection, a banner appears atop your display area. This also provides access to the conversion utility:



Ribbon Standardization



Following your requests to adopt a more consistent ribbon layout between Studio products for core (shared) commands, we've made a few changes for this update. This means your familiarity with one Studio is now useful if using another product in the Studio range. Where possible, we have standardized command grouping and positions for the **Data**, **Format** and **3D View** ribbons. We've maintained specific layouts where a particular operating domain demands it, such as grade estimation, resource modelling, pit design and field mapping functions, so these aren't changing.

We will continue to standardize our ribbons, where appropriate, in future releases.


Early Access Features

Advanced Digitizing Controls


As part of a wider campaign to improve and extend our digitizing tools, we've introduced a new way of creating new string data in this update, and we'd love to know what you think before we finalize things.

`new-string`, arguably the most commonly used design command in any Studio product, has been extended over the years and also supported by a range of other design functions to enhance more 'managed' digitizing often required in the mine planning domain, where design drafting with precise string properties can be critical to an effective design and schedule. The `extend-string` command has been similarly enhanced.


`new-string` and `extend-string` can run in an enhanced mode in this update. By default, both commands behave as before, but there's a new project setting that allows advanced settings to be applied during digitizing to constrain the orientation of the next string segment you create. Located on the **Points and Strings** screen, check **Show advanced digitizing controls** to activate enhanced mode for **new-string** and **extend-string**:



The next use of either command displays a popup allowing you to constrain the length, azimuth and gradient of the next string edge. For constrained angle changes, you can also ensure azimuth changes are made in fixed amounts from the previous string segment:



This can help to ensure operational and design constraints are honoured during digitizing, saving time later by editing and adjusting design data. Help files for both commands have been updated to explain how to use the new controls. You can also press F1 when the new popup displays during digitizing.



Please let us know what you think of this early-access feature. We value your feedback!

Other Command & Process Updates

- COPYMOD now supports retrieval criteria.
- smooth-gradient can now be used to fully smooth (start to end) preselected strings.
- REBLOCK now supports retrieval criteria

- `INTEXT` can now process data using either a data definition (INDD) file or a `SETTINGS` file, or neither.
- `WIREFILL` now supports retrieval criteria.

All Improvements

Commands & Processes

- **STUDIO-7369** By default, all implicit modelling commands now default to snap surface data to the drillhole milestone data positions.
- **STUDIO-7338** The fixed colour legend used, when colouring by group with the Create Contact Surfaces command, has been improved.
- **STUDIO-7334** When defining an estimation, you can now choose between Flay lying (horizontal or sub-horizontal) or Inclined (dipping) structural orientation.
- **STUDIO-7300** The COKRIG help file has been extended to include more information about VREFNUM, VSETNUM in input parameter files.
- **STUDIO-7317** When importing estimation and field parameters files into Advanced Estimation, grades are now preselected if possible.
- **STUDIO-7253** The Project Data bar now features 3D and Plots folder items.
- **STUDIO-7221** You can now colour **Contact Surface** symbols, additional points, output surface and output contact points using the colour of the stratigraphy.
- **STUDIO-7180** You can now manage additional points for the Categorical command in a script.
- **STUDIO-7178** You can now use the **Show Samples** function to view samples contributing to a particular estimation, using new controls on the **Estimate** ribbon.
- **STUDIO-7094** Control the density of your output contact surface using new Resolution controls.
- **STUDIO-6801** The default discretization for angle estimation by Inverse Distance is now 1x1x1.
- **STUDIO-6584** In Advanced Estimation, left or right spaces are trimmed from the field names while reading the field's parameter file.
- **GEO-823** The Update Surface function in Categorical and Implicit Modelling no longer creates a new surface if one already exists.
- **GEO-720** You can now choose to model all, selected and/or visible data in any of the implicit modelling commands (Vein, Contact Surface, Categorical Value and Grade Shells).

- **CORE-9827** .dmx.tmp files are now ignored by the **Project Files** and **Project Data** control bars.
- **CORE-9775** As part of the project to standardize Studio ribbons, icon updates have been made.
- **CORE-9732** Read-only DM files are now converted to read-only DMX files during project or utility-initiated conversion.
- **CORE-9711** Documentation for EXTRA's RAND and RANDBETWEEN numeric functions has been improved.
- **CORE-9649** Block model fields in the Text Importer are now ordered more sensibly.
- **CORE-9604** The default field of view angle for new projects is now 45 degrees (set-view-fov command).
- **CORE-9586** To increase system security, we have blocked the display of online content in the Customization window.
- **CORE-9583** In Files, Fields and Parameters screens running in Dark mode, text in dropdowns is now more readable.
- **CORE-9579** COMPDH now supports up to 5 ZONE fields to composite within, and five optional fields DOM1 to DOM5 can now be specified to record dominant categorical values (by length) within each composited sample.
- **CORE-9578** The Script Recorder now generates syntax that aligns with Datamine's safer scripting policy.
- **CORE-9574** The legacy script converter utility has been removed from product distributions.
- **CORE-9561** Rationalization of baggage files for help systems means Studio installation file sizes are now smaller.
- **CORE-9551** The **Datamine Studio Script Updater** has been provided to automatically convert your scripts to more protected versions.
- **CORE-9550** The Studio scripting environment now offers a safer scripting syntax, minimizing the potential impact of malicious thread actors.
- **CORE-9546** New calculated (virtual) fields are now available to calculate the dip angle (**_PDIP**) and direction (**_PDIPDIR**) of the best fit plane through a data object.
- **CORE-9542** A more secure mechanism for data object automation has been implemented. Consult your online help for more details.
- **CORE-9540** You can delete selected 3D overlays of the Project Data using the <DELETE> key.



- **CORE-9539** The **CalculateEdgeMetrics()** method now calculates values for the final edge of a closed perimeter.
- **CORE-9528** The Plots window **Section** and **View** ribbons now have new icons.
- **CORE-9526** It is now quicker to read and process DMX files containing alphanumeric columns.
- **CORE-9522** `WIREFILL` now supports retrieval criteria.
- **CORE-9521** `COPYMOD` now supports retrieval criteria.
- **CORE-9519** `REBLOCK` now supports retrieval criteria.
- **CORE-9490** The Text Importer can now be automated using any Studio product.
- **CORE-9482** The `switch-drillhole-points-traces` command is now available on the Format ribbon (Display Mode group).
- **CORE-9474** The **Text Importer** and `INTEXT` documentation has been extended and corrected.
- **CORE-9473** `INTEXT` can now process data using either a data definition (INDD) file or a SETTINGS file, or neither.
- **CORE-9449** The **CENTRE** file for the `ELLIPSE` process is no longer dependent on search, variogram or zone parameter file inputs.
- **CORE-9409** An issue causing an unsorted block model to become locked after a previous attempt to load it has been resolved.
- **CORE-9398** In `COMPDH` it has always been the case that if the **LENGTH** field in the input sample file is not equal to **FROM - TO** the **LENGTH** field is set to **TO - FROM**. This behaviour remains, but a maximum of 10 messages are issued in a process run.
- **CORE-9383** The **3D View** ribbon layout is now consistent between Studio products.
- **CORE-9382** The **Format** ribbon layout is now consistent between Studio products.
- **CORE-9378** The **Data** ribbon layout is now consistent between Studio products.
- **CORE-9359** Your product now includes a new control bar: **Project Data**. This combines the power of previous bars to categorize and display files, loaded objects and plot data.
- **CORE-9391** When using the Text Importer, you can now import alphanumeric trace and absent values into a destination field that is numeric.

- **CORE-9340** Unload all overlays of a specific data type using a new **Sheets** and **Project Data** control bar menu option.
- **CORE-9301** Legend controls within various screens have been reverted to more popular legacy behaviour (with improvements) and restyled.
- **CORE-9277** Quick Filter drop down lists now inherit the current look and feel theme.
- **CORE-9252** Project data bar icons for the Plots and 3D folders have been updated.
- **CORE-9233** By request, flat-rendered wireframes are now less shiny.
- **CORE-9229** **Text Importer** scenario files (.dminsv) now appear in the Project Data control bar.
- **CORE-9228** If opening a Text Importer scenario, file detection has been improved and you can now browse for missing files.
- **CORE-9103** The **Project Data**, **Loaded Data** and **Holes** control bars now inherit visual themes.
- **CORE-9097** An issue that could make data picking difficult where data was precisely coincident with the section plane has been resolved.
- **CORE-9082** **Drillhole Importer** now recognizes "Hole_ID" as a BHID mapping type.
- **CORE-9014** All commands relating to the obsoleted **Visualizer** window have been removed from the application.
- **CORE-8999** Tooltips have been added to the **Group Lithology** and **Assign Lithology** tasks.
- **CORE-8980** When adding a new unique value legend item in the New Legend Wizard, you can now add any other colour to the current palette.
- **CORE-8839** Documentation on snapping to a grid has been improved.
- **CORE-8805** File case names are now preserved in the default overlay when dragging and dropping files into the 3D window.
- **CORE-8763** 3D properties and similar screens now use a clearer and expanded toolset for legend management. See your help file for more details.
- **CORE-8699** An issue causing the `insert-by-segment-length` to fail when working with large data has been resolved.
- **CORE-8673** Issues causing unpredictable selection behaviour (or presentation of selected data) in the Plots window have been resolved.
- **CORE-8654** Selecting the outer boundary of a plot sheet now enables the **Manage** ribbon (not the **Home** ribbon as previously).

- **CORE-8625 Drillhole importer** now recognizes more field names when automatically mapping to system fields.
- **CORE-8519** Studio Data, Report and 3D View ribbons have been made standard in all Studio products other than Studio Mapper.
- **CORE-8510** The **Project Data** control bar now displays files external to the project folder with the same vertical line indicator as the Project Files control bar.
- **CORE-8196** `MODSPLIT` can now output either **MODELOUT**, **FULLMOD** or both. Previously, both outputs were always generated.
- **CORE-8143** It is now quicker to close a project without saving it.
- **CORE-7746** A new command `digitise-doughnut` lets you create complex string data in relation to an external perimeter and one or more closed internal strings.
- **CORE-7506** The **Drillhole Planner** now inherits the current visual theme.
- **CORE-7272** The **Edge Editor** is now available in this product. Use it to dynamically adjust string edges.
- **CORE-6637** This update features early access to a preview of our advanced string digitizing controls. Constrain the azimuth, length and gradient of new string segments as you draw. Enable this beta functionality using the **Project Settings** screen.
- **CORE-5878** The Project Data bar now permits multiple item selection.
- **CORE-5550** `smooth-gradient` can now be used to fully smooth (start to end) preselected strings.
- **CORE-1878** You can now import or load multiple files in one operation using new multi-file options.
- **GEO-718** The layout of the **Drillhole Importer** screens has been improved.

Utilities & Supporting Services

- **CORE-9629** This update includes an upgrade to the mesh wireframing engine (2.0.2.54).
- **CORE-9577** Your product installs a major update to License Services (7.0). This introduces encrypted traffic options for enhanced data traffic security.
- **CORE-9536** The Start Page environment has been made more secure.
- **CORE-9481** Data Source Drivers now export virtual data columns.
- **CORE-9362** If using the DmFile SDK, reading and writing records is now twice as fast as before.

- **CORE-8826** You can now import MineScape prism models where data overlaps in Z.
- **CORE-8524** An encrypted traffic option is now available to License Services server administrators. Requires a compatible client installation (7.0 or higher).
- **CORE-8524** We have added a new driver! Import UBC voxel model data using the new **Geosoft** driver option.
- **CORE-8160** The MineScape Block Model Importer has been added to the Data Import screen as a new driver: "MineScape strata model".
- **CORE-6521** You can now import and load Leapfrog mesh and project model file data using a new Data Source Driver.
- **MSO-1558** Documentation for MSO version 5.0 has been completed for this version.
- **MSO-1581** Evaluation method descriptions on the **Report** screen have been updated for consistency and clarity.



Defect Fixes

- **STUDIO-7385** When editing contact surface samples for the first time in a project session, the Apply button is now correctly enabled.
- **STUDIO-7370** An issue preventing `VCONTOUR` from processing DMX files correctly has been resolved.
- **STUDIO-7363** When using `ANISOANG` with a flat wireframe, variogram model with rotation on Axis-3 in a 3-1-3 rotation no longer produces an unexpected result.
- **STUDIO-7350** The `COKRIG` help file information on **USEPK** and **SAMPOUT** has been corrected to show correct valid values.
- **STUDIO-7239** Evaluation ribbon options are now correctly enabled for evaluation against drillhole data.
- **STUDIO-6957 COUNTFLD** defined in soft boundary/custom zones (zpar file) is now being output correctly in `COKRIG` block models.
- **STUDIO-6754** An issue preventing variogram fitting of variograms generated via the VGRAM process has been resolved.
- **GEO-720** You can now choose to model all, selected and/or visible data in any of the implicit modelling commands (Vein, Contact Surface, Categorical Value and Grade Shells).
- **CORE-9921** EXTRA's `FLDFAIL` parameter's default value of 1 has been reinstated (previously 0) to match earlier application versions.
- **CORE-9919** An issue causing system failure, if v1 or v2 commands were used in conjunction with plane alignment options, has been resolved.
- **CORE-9875** An issue preventing the initial display of colour chips on the Assign Lithology screen has been resolved.
- **CORE-9868** A data-specific issue causing Deswik import to fail has been resolved.
- **CORE-9855** An issue causing issues when snapping and zooming in conjunction with vertical 3D scene exaggeration has been resolved.
- **CORE-9826** An issue preventing the successful import of Deswik wireframe data has been resolved.
- **CORE-9761** Picking of data symbols rendered in 2D in screen space can now be selected as normal.
- **CORE-9745** An issue causing `REBLOCK` to delete the input block model, if additive fields are used, has been resolved.

- **CORE-9717** The Project Data Bar's "Create from Loaded Data" menu option now works as expected.
- **CORE-9716** Grids and Sections folders can no longer be removed from the Project Data bar.
- **CORE-9714** An issue causing the incorrect rendering of 3D drillhole cylinders has been resolved.
- **CORE-9710** Modeless dialogs are now reset as expected when a default profile is reinstated.
- **CORE-9700** When translating strings, points or wireframes, decimal values now persist correctly between dialog sessions.
- **CORE-9673** 3D overlay group projections in Plots now react immediately to Project Data or Sheets control bar changes.
- **CORE-9670** The UNFOLD wizard now has context-sensitive help.
- **CORE-9653** When importing DXF/DWG points data, the 'Include Hatches' option is no longer displayed.
- **CORE-9642** 3D window axis and scale indicators now hide and show immediately following window configuration changes.
- **CORE-9631** The INTEXT process no longer stalls indefinitely if settings are unexpected.
- **CORE-9622** An issue causing SELWF to run more slowly than expected has been resolved.
- **CORE-9618** An issue causing move-points to pick an incorrect target has been resolved.
- **CORE-9615** An issue preventing the import of a Vulcan block model has been resolved.
- **CORE-9613** An issue causing incorrect display of Information Mode output, if the 3D view was orthogonal to the active section, has been resolved.
- **CORE-9595** The Command Toolbar contents are now more easily visible in Dark mode.
- **CORE-9582** The Move String command is now available again on the ribbon.
- **CORE-9562** Crash reports are now registering successfully in Freshdesk.
- **CORE-9537** DMX files input to transform-coordinates now generates output files usable by Datamine Supervisor.
- **CORE-9518** You no longer see an empty message box when trying to save an object to an open DMX file.

- **CORE-9517** The Text Importer is now storing the Delimiter correctly if not a comma.
- **CORE-9509** The Text Importer now reads fixed width values correctly.
- **CORE-9503** "Ignore Clipping" instructions at the overlay level are now applied immediately.
- **CORE-9499** An issue preventing string editing in plan view with >1 exaggeration in Z has been resolved.
- **CORE-9419** The Point Cloud Reconstruction wizard now automatically generates a scenario on entering a new scenario name.
- **CORE-9403** An issue causing the incomplete display of model cells in intersection at some section orientations has been resolved.
- **CORE-9370** An issue causing unexpected data rounding in `TRIFIL` has been resolved.
- **CORE-9357** `WIREFILL` now correctly interprets default plane information, and a `@PLANE` parameter is added to allow behaviour override.
- **CORE-9353** An issue causing `SELWF` to fail when processing retrieval criteria has been resolved.
- **CORE-9348** The select-perimeter command no longer behaves inconsistently when called from a script.
- **CORE-9264** An issue causing incorrect IJK values to be generated via the Text Importer has been resolved.
- **CORE-9236** An issue causing the incorrect alignment of a georeferenced image has been resolved.
- **CORE-9231** An issue preventing the successful reinstatement of a UI profile has been resolved.
- **CORE-9100** When transforming coordinates, and converting EPSG 5533 to WGS 84 and exporting to Earth, Lat/Long columns are no longer inverted.
- **CORE-9012** When transforming geographic coordinates, you can now generate output files on a non-primary drive.
- **CORE-8952** The zoom command now accurately centers the screen if the scene is exaggerated.
- **CORE-8794** An issue causing clipped block model data to be rendered invisible, when the clipping section deviates from the major axes, has been resolved.
- **CORE-8696** An issue causing smooth-gradient (`smg`) to fail with a large string data file has been resolved.

- **CORE-8632** Importing Deswik wireframe data now imports all available attributes. Previously some were not imported.
- **CORE-8582** An issue causing unexpected view navigation in scenes with vertical (Z) exaggeration has been resolved.
- **CORE-8259** 3D window section clipping is now reapplied correctly when the section corridor width is changed.
- **CORE-8052** An issue causing **SAMPOUT** to be created incorrectly when writing alphanumeric fields has been resolved.
- **CORE-7929** 3D plot overlay labels now react to clipping settings as expected.
- **CORE-6800** Studio now supports the concept of a temporary session-only data attribute.
- **CORE-5413 REBLOCK** no longer fails if there is a space in the file in the project folder.
- **CORE-5270** Unable to cancel (ESC Key) Set Section about a single point
- **CORE-5137** Adding a trailing space to a new project name no longer causes Studio to create 2 project folders.



Studio RM 3.0.1 Release Notes

This is a hot fix patch for the previous 3.0 version and includes important fixes and improvements.

All Improvements

Commands & Processes

- **STUDIO-7314** A MERGEEST parameter has been added to COKRIG to control whether estimations are merged prior to an estimation run, or calculated separately.
- **STUDIO-7314** COKRIG now completes more quickly when grade capping is applied.
- **STUDIO-7296** A "Use search distance anisotropy" check box, checked by default, is now available for the Nearest Neighbour estimation method.
- **CORE-9530** You can now choose if files in project subfolders are converted to the default file format on project launch.
- **CORE-9460** Saving block model data to the project is now much quicker.

Automation

- **STUDIO-7319** You can now set the name of an output boundary string object with the **Create Vein Surface** command (OutputBoundaryFile=ObjectName).

Defect Fixes


- **CORE-9575** An issue causing TRIFIL to corrupt input data if forcibly closed early has been resolved.
- **CORE-9541** An issue causing SLIMOD to fail with .dmx inputs has been resolved.
- **STUDIO-7302** An issue causing slow loading of a prototype model via COKRIG (and Advanced Estimation) has been resolved.
- **STUDIO-7291** When using dynamic anisotropy with COKRIG, the calculated TMINDIST field no longer uses the static ellipse given by the spar file, but

instead of the dynamic orientation coded into the model by the DA workflow, as expected.

- **STUDIO-7261** Average Distance is now properly calculated when using Unfolding in COKRIG.
- **STUDIO-7260** An issue preventing KNA from displaying expected results in Advanced Estimation has been resolved.
- **STUDIO-6471** An issue preventing the display of some variograms directions in the Fit tool has been resolved.
- **CORE-9507** An issue causing INPDDF to incorrectly generate a Datamine wireframe from Leapfrog ASCII data input, has been resolved.
- **CORE-9462** Loading data objects no longer incorrectly flags them as modified, triggering unnecessary save data prompts on closedown.
- **CORE-9501** Files created by the DMtoDMX conversion utility can now be loaded into Datamine Supervisor.
- **CORE-9444** An issue causing clip-strings-to-wireframe to fail on some data has been resolved.
- **CORE-9357** WIREFILL now correctly interprets default plane information, and a @PLANE parameter is added to allow behaviour override.
- **CORE-8052** An issue causing SAMPOUT to be created incorrectly when writing alphanumeric fields has been resolved.

Studio RM 3.0 Release Notes

New Datamine File Format



The Datamine file format used natively by Studio products originated from Datamine's "Native File System" over thirty years ago. It has been maintained and supported by Datamine products since then. The mining industry has seen a significant increase in data volume and complexity during this time, which has started to strain the capabilities of the Datamine format.

Our response to this challenge is a new file format that is more suitable for the current and future data requirements of the mining industry. This format has a new file extension; .dmx.


Files are smaller and now supports up to 2048 columns. Your application generates .dmx files by default (this can be changed on the **System Options** screen. Both legacy (.dm) and new .dmx format files can be read. Other improvements will follow, as our new format is highly extensible and provides many opportunities to make data handling easier and smarter in the future.

The new format integrates smoothly with modern Studio products and your existing workflows and customization scripts, and the Table Editor can be used to view both legacy and new formats. For bulk file conversion, there's even a useful DM to DMX file conversion utility in the **Data Converter** installation folder should you wish to batch convert input files.

You can recognize .dm and .dmx files in the **Project Files** control bar:

	.dmx file	A file in the proprietary .dmx Datamine binary file format.
	.dm file	A file in the legacy .dm Datamine binary file format.

Plots Overhaul



We've made major changes to the way plots are constructed with this update.

Plots are formed from a collection of plot items, ranging from 3D projections and associated sections, to clip art, text boxes and so on. You asked us to improve the usability of these tools so we've taken a step back and changed our approach to reporting. In a good way.


Plot items are now supported by their own ribbons, displayed whenever a particular plot item is selected, be that a projection, a north arrow, title box or whatever. With your help, we analysed the most commonly-used features and settings and have created a dedicated ribbon of tools for each plot item type. For example, managing the tabular contents of title box cells is now much easier thanks to handy cell managers.

The **Plots (Manage)** and **Plots (View)** ribbons have also been combined.

Residual Composites

COMPDH now supports residual outputs and has a new method for including residuals in the composite output.

3D Window Improvements



The display of large data so that it has a lower impact on system and application performance. This includes new, smart settings to control how and when 3D scene data is rendered, making sure the system only has to draw what it needs to. To support these changes, new 3D options have been introduced to control **Environment Settings** (automated scene clipping) and a **Render on Demand** setting (on by default), added to the 3D system settings screen.

Assign Lithology Improvements


The **Assign Lithology** command's new **Paint** mode lets you iteratively apply drillhole attribute values using standard 3D data selection methods. This can make drillhole coding a lot quicker where you want to interactively assign new attribute values to multiple drillhole segments.

During implicit modelling, drillhole coding changes (via assign-lithology) are also now reflected instantly in the HW/FW/Intercept indicator symbols.

We've also added a shortcut to control whether selected 3D data is appended or alternated when the CTRL key is used, plus a new command **assign-lithology-assign** (quick keys "ala") which can be used to quickly apply the active lithology of the **Assign Lithology** screen to selected drillhole data.

Filled Wireframe Intersections (Preview)

We've added a new wireframe formatting option to the Wireframe 3D Properties screen: **Fill intersection**.



Wireframe data shown with standard clipping and filled intersection mode

Now, you can display clipped wireframes with solid intersections, emulating a 'filled' volume. This can be really useful when visualizing volumes in cross section.

Note: This feature is still in development, but we thought we'd let you have a look at progress so far. There are some limitations, such as viewing intersections of multiple coincident intersection planes of different colours, but it should give you an idea of what we're aiming for.

Text Importer

Data Definition Mapping: `_vb_collars.txt`

Data definition: Collars

Include	Column Name	Mapped Type	Output Name	Type	Length	Default	Implicit
<input checked="" type="checkbox"/>	BHID	✓ BHID	BHID	Alpha	8	0	N
<input checked="" type="checkbox"/>	XCOLLAR	✓ XCOLLAR	XCOLLAR	Numeric	0	0	N
<input checked="" type="checkbox"/>	YCOLLAR	✓ YCOLLAR	YCOLLAR	Numeric	0	0	N
<input checked="" type="checkbox"/>	ZCOLLAR	✓ ZCOLLAR	ZCOLLAR	Numeric	0	0	N
<input checked="" type="checkbox"/>	ENDDEPTH	None	ENDDEPTH	Numeric	4	-	N
<input checked="" type="checkbox"/>	REFSYS	None	REFSYS	Alpha	8	-	N
<input checked="" type="checkbox"/>	REFMETH	None	REFMETH	Alpha	4	-	N
<input checked="" type="checkbox"/>	ENDDATE	None	ENDDATE	Alpha	12	-	N

Import one or multiple text files using a new **Text Importer** screen.


Select as many files as you need to import and configure all importation options on a single screen, including automated and interactive field mapping for your selected data type and preview your file before you import.

Once you're happy with your settings (which can be set for each individual file if required), store your configuration information in a handy scenario file which can be used to consistently import data in the future and to share with others in your organization.

Datamine File Tags

With the introduction of the new DMX file format in this version (see above), a new facility arrives for all users; table tagging.

We intend to make use of this new feature in the future, but you can also add your own data tags and values to any .dmx file using the Table Editor, which includes a new **Tag Editor** function on its toolbar:



Add as many tags and associated values as you like. This could be useful, say, to embed the status of a model or other design files, or to provide some implicit spatial context to data (mine, area, level, for example) without requiring additional data attributes.

New Processes & Commands

- **COMBTRI** allows up to 20 wireframe files to be combined in a single operation.
- **INTEXT** – You asked for a file-based process to convert text files to Datamine files, so we created **INTEXT**. Either using the data definition specified in the incoming file, or by choosing the definition of another file, import text data using a range of options.

Command & Process Improvements

- **extend-segment-virtual-intersect** can now be used on closed strings.

All Improvements

Commands & Processes

- **Multiple Cases** Your product can now read and write the new Datamine binary format (.dmx) and will automatically convert non-default files in the project folder when a project is opened.
- **Multiple Cases** A new scenario-based **Text Importer** lets you import (single or batch) text files as a specified data type.
- **Multiple Cases** Several improvements and fixes have been made to improve 3D window visualization.
- **STUDIO-7229** We've added a shortcut to the **Assign Lithology** screen to control whether selected 3D data is appended or alternated when the CTRL key is used.
- **STUDIO-7226** During implicit modelling, drillhole coding changes (via assign-lithology) are now reflected instantly in the HW/FW/Intercept indicator symbols.
- **STUDIO-7228** The **Assign Lithology** command's new **Paint** mode lets you iteratively apply drillhole attribute values using standard 3D data selection methods.
- **STUDIO-7227** A new command **assign-lithology-assign** (quick keys "ala") can be used to quickly apply the active lithology of the Assign Lithology screen to selected drillhole data.
- **STUDIO-7183** When processing categorical and grade shell scenarios, user feedback (errors, warnings) are improved.
- **STUDIO-7009** Project Settings have been added to support MineTrust-enabled projects.
- **STUDIO-7008** The New Project Wizard now lets you pick a MineTrust-aware project.
- **GEO-426** When re-running Drillhole Importer, previously generated legends can now either be recreated, or previous legends reinstated as default legends for the target field.
- **CORE-9364** Coding drillholes using the Assign Lithology command is now more responsive.
- **CORE-9284** If you create a project using a folder that contains files in a non-native format, they are automatically converted.

- **CORE-9265** By popular request, the "red" quick key combination now launches reduce-points (not simplify-string) as in previous versions. Menu options have also been reinstated.
- **CORE-9240** Plot item locations now remain static when adjust the Relative positioning option for locatable plot items.
- **CORE-9239** You can now interactively pick the target position of a locatable plot item using a new Anchor ribbon button.
- **CORE-9234** DMX data saved from a Studio application now embeds the creating product and version as metadata (tags).
- **CORE-9112** Studio project startups now include a check for local project files in a non-default format, and converting them to the default format.
- **CORE-9030** The new-polygon command has been added to the Digitize ribbon.
- **CORE-9021** Your product's Mesh wireframing library has been updated to version 2.0.1.53.
- **CORE-9006** You can now use the "uc" quick key combination to apply clipping in Plots sheets.
- **CORE-8995** A new Paint Mode has been added to Assign Lithology.
- **CORE-8938** A warning is now displayed when running HOLES3D when the BHID value in the Collar and Survey files doesn't match.
- **CORE-8929** Loaded data objects that have metadata tags display those tags in the Properties control bar.
- **CORE-8918** Supporting plugins for PTCLD2WF and the Point Reconstruction Wizard have been updated.
- **CORE-8895** In the Project files control bar, when using the context menu on a macro file that contains more than 9 macros, Studio doesn't crash and works as expected.
- **CORE-8876** You can now choose to manually or automatically adjust 3D window clipping planes using the Environment Settings screen.
- **CORE-8860** The "red" quick key combination now runs the **simplify-string** command, not the legacy reduce-points command. Ribbon access has also been updated.
- **CORE-8702 query-angle** now outputs angle information in degrees, minutes and seconds.
- **CORE-8697 intersect-drillholes-wireframes** now outputs the intersection angle between drillhole and wireframe.

- **CORE-8556** You can now create a template Unfolding Parameter File in the Table Editor. This file type is now also recognized by the Project Data bar.
- **CORE-8503** Implicit modelling commands, including lithology grouping and assignment, are now modeless and can be launched simultaneously.
- **Cases: CORE-8490, CORE-8452, CORE-8357** Front & back 3D window clipping distances now computed automatically based on object's bounding box.
- **CORE-8465** Context-sensitive **Section** and **View** ribbons now support projection editing and creation in the Plots window.
- **CORE-8460** The **Plots (Manage)** and **Plots (View)** ribbons have been combined.
- **CORE-8424** Quick filtering wireframes and block models is now much quicker.
- **CORE-8310** By default, data is now rendered in the 3D view only when required. This makes application usage with large data much quicker with more responsive controls.
- **CORE-8216** An **Anchor** ribbon has been introduced to support locatable plot items.
- **CORE-8206** Reloading and refreshing large data objects is now quicker.
- **CORE-8181** Exporting Plots window data to CAD formats has been completely overhauled to provide support for a wider range of data configurations and to improve accuracy for all exported data types.
- **CORE-8093** Improvements have been made to the way strings and points are rendered in the 3D window, to improve performance.
- **CORE-8047** Changes to the Plots ribbons will now be automatically shared with all Studio products, making forward development quicker and easier.
- **CORE-8012** A new context-sensitive Text Cell ribbon has been created to modify the contents of text cells in title boxes.
- **CORE-7966** You can now overwrite an existing legend instead of having to specify an unused/unique legend name.
- **CORE-7946** Legend box plot item formatting can now be performed using a new Legend Box context-sensitive ribbon.
- **CORE-7732** A new **Text Importer** screen lets you import multiple ASCII text files with per-file configurations and share your importation settings as a scenario.
- **CORE-7694** Symbol plot item formatting can now be performed using a new Symbol context-sensitive ribbon.

- **CORE-7693** Text Box formatting can now be performed using a new Text Box context-sensitive ribbon.
- **CORE-7692** Title box formatting can now be performed using a new Title Box context-sensitive ribbon.
- **CORE-7691** Scale bar formatting can now be performed using a new Scale Bar context-sensitive ribbon.
- **CORE-7690** North arrow formatting can now be performed using a new North Arrow context-sensitive ribbon.
- **CORE-7279** **extend-segment-virtual-intersect** can now be used on closed strings.
- **CORE-7161** The Create Model Prototype screen now has additional support for both new and copied rotated model prototypes.
- **CORE-7051** **COMPDH** now lets you save residual composites to a new &RESIDUAL output file option.
- **CORE-6906** When creating a ramp string, if the Distance set is less than the minimum segment length, a partial segment is added.
- **CORE-6654** Group Lithology mappings are now saved while the project is open and also if the project is closed. These settings are reinstated with the next use of the command.
- **CORE-2410** A new process - **INTEXT** - converts text files to Datamine files using an existing data definition and other parameters.
- **CORE-231** We've added a new wireframe visualization option; **Fill intersection**.
- **CORE-68** A new command - **clip-strings-to-wireframe** - lets you trim string data in relation to a wireframe surface or volume.

User Experience

- **STUDIO-7223** Studio RM product logos have been updated.
- **GEO-528** In the Drillhole Importer, all table columns are now immediately visible.
- **CORE-9108** The Quick Filters screen now inherits the selected look and feel option.
- **CORE-9086** The INTEXT text import process has been added to the Data ribbon
- **CORE-9085** Combine Wireframes (COMBTRI process) has been added to the Wireframe ribbon.

- **CORE-9084** Clip String to Wireframe has been added to the Digitize ribbon.
- **CORE-8973** The Project Files control bar now differentiates .dm and .dmx formats by distinct icons.
- **CORE-8937** The Project Files and Project Data control bars now display up to 30 macros in a .mac file.
- **CORE-8935** A new splash screen has been implemented.
- **CORE-8906** Large Data Mode has been relabeled "Keep data in front of the camera" to make it clearer what it does.
- **CORE-8851** The Table Editor now supports visual themes.
- **CORE-8765** The **Georeference Objects** screen now inherits current look and feel settings.
- **CORE-8742** Images and colour scheme have been updated for the New Project Wizard.
- **CORE-8499** The Group Lithology and Assign Lithology screens now inherit the current visual theme.
- **CORE-7184** A new 'Dark' look and feel theme is now available in Studio RM.
- **CORE-8601** The Project Data bar now displays the first level of available folders by default.
- **CORE-8488** Icons for the visualization window tabs and control bars have been updated.
- **CORE-5599** Managed task windows, such as implicit modelling and lithology assignment tasks, now persist their docked UI status between project sessions.

Automation

- **Multiple** Scripted access to Datamine files has been extended to manage both legacy and new DMX file processes.
- **STUDIO-7117** If executing scripts for implicit modelling, more information is now provided about parameter usage.

Utilities & Supporting Services

- **CORE-8915** ALS Coreviewer options have been removed from this product. Datamine no longer resells ALS Coreviewer.
- **Case: CORE-8759** End User License Agreement references have been replaced with Terms and Conditions.

- **CORE-8747** You can now associate meta data with .dmx files using the Table Editor. This facility is not available for legacy .dm files.
- **CORE-8585** You can now import up to 256 fields via the Surpac driver, and you are alerted if this limit is exceeded.
- **CORE-8564** The obsolete command erase-wireframe-surface has been removed from the ribbon system.
- **CORE-8439** A standalone utility has been created to convert .dm to .dmx files.
- **CORE-8329** A new method more accurately calculates the volume of Prismatic models, as imported by the MineScape Importer utility (minescape-to-blockmodel command).
- **CORE-6986** .xyz files can now be imported when importing Text files to the project.

Documentation & eLearning

- **STUDIO-7232** Create Vein Surfaces and Create Contact Surfaces automation help has been expanded to include section plane parameters.
- **STUDIO-5486** The SGSIM help file has been extended.
- **STUDIO-4883** The help file describing rotated models in grade estimation has been updated to make the exclusion of folded data clearer.
- **STUDIO-3940** More information about the maximum distance threshold for variogram calculations has been added to the Create Variograms screen (Adv. Estimation) help file.
- **CORE-9348** EXTRA help files, including the examples topic, have been updated for clarity and consistent terminology.

Additional Defect Fixes

- **STUDIO-7304** An issue causing COKRIG to fail, while checking for sample compatibility for merging the estimation, has been resolved.
- **STUDIO-7299** Outlier capping is now functioning as expected for all estimations.
- **STUDIO-7231** In Advanced Estimation, the Number of Holes output field is no longer unexpectedly reset to default when displaying the Run Estimation screen.
- **STUDIO-7213** A data-specific issue causing incorrect estimated values using soft boundary estimation has been resolved.
- **STUDIO-7102** Issues making it difficult to use point Kriging in Advanced Estimation have been resolved.
- **STUDIO-7020** An issue preventing MINDIST and AVEDIST fields being populated by COKRIG, in some cases, has been resolved.
- **CORE-9285** An issue that could cause system failure, when rapidly deleting project files via the Project Data bar, has been resolved.
- **CORE-9000** Enabling and disabling values in Assign and Group Lithology tasks now shows and hides drillhole intervals as expected.
- **CORE-8996** An erroneous "No field selected" message no longer appears on the Assign Lithology screen after lithology values have been picked.
- **CORE-8958** An issue preventing **GETSAMP** from functioning correctly has been resolved.
- **CORE-8947** 1-letter macro file names now appear in the Project Files control bar as expected.
- **CORE-8947** SELWF now produces expected results when there are spaces in the field name values of ZONE.
- **CORE-8867** An issue preventing the successful installation of License Services on some Windows Server platforms has been resolved.
- **CORE-8848** The double-sided 3D wireframe rendering setting is now correctly saved to the project.
- **CORE-8811** An issue caused by swapping Snap Mode settings has been resolved.
- **CORE-8784** Wireframes generated by **SWATHPLT** now include consistently oriented triangles.
- **CORE-8783** Making a plot item locatable no longer unexpectedly changes that plot item's position.

- **CORE-8774** Implicit modelling screen expandable groups now appear correctly on 4K monitors.
- **CORE-8757** An issue causing **PPQQPLOT** to fail with a large input file has been resolved.
- **CORE-8754** An issue causing system shutdown after reordering georeferencing table values (**georeference-objects**), has been resolved.
- **CORE-8675** An issue causing **converge-segments** to display unexpected results after undoing the operation has been resolved.
- **CORE-8670** The **BOOLEAN** process no longer fails when the two inputs (in the same run) have a column with the same name but a different data type.
- **CORE-8610** 3D object bounding boxes, used for 3D view configuration are now set correctly for all string object entities.
- **CORE-8583** An issue causing an orthographic 3D view corruption where the front clipping plane distance is very large, has been resolved.
- **CORE-8530** An issue causing system instability, when clipping in the Plots window using a quick key, has been resolved.
- **CORE-8523** An issue attempting to print screen contents when Info Mode is active has been resolved.
- **CORE-8479** In Plots, setting a primary clipping width to a value larger than the extent of the section no longer causes the midpoint to be moved outside of the section extents.
- **CORE-8475** An issue causing unexpected behaviour when snapping at high zoom levels has been resolved.
- **CORE-8199** When exporting plot data in a vector format, labels are now position correctly if not exported as vectors.
- **CORE-8087** An issue that could cause a progressive memory leak when reloading a data object has been resolved.
- **CORE-7713** An issue preventing the automatic generation of legends by data type has been resolved.
- **CORE-7645 HOLES3D** now considers dip and bearing information from both a survey and collars file, prioritizing the survey file information. DIPMETH is applied to all data, regardless of source.
- **CORE-6591** A repetitive warning message in Table Editor relating to undo operation performance can now be disabled as expected.
- **CORE-6375** When exporting plot data in vector format, grid data is now exported correctly.

- **CORE-6002** An issue preventing the update of associated screens after renaming 3D overlays has been resolved.
- **CORE-5460** When exporting plot data to a CAD format, precision issues no longer occur when world coordinates are disabled.
- **CORE-3477** You can now generate a 2 point vertical plane by selecting 2 vertically-aligned points.



Datamine enables efficient and sustainable mining through the application of world-leading technology and services.

Read the Docs

docs.dataminesoftware.com

Get in Touch

www.dataminesoftware.com/contact

www.dataminesoftware.com/support

